

# Electrostatic Potential And Capacitance

---

## Electrostatic Potential energy

- Work done by an external force in bringing a charge  $q$  from a point R to a point P in electric field of a certain charge configuration is  $U_P - U_R$ , which is the difference in potential energy of charge  $q$  between the final and initial points.
- Potential energy at a point is the work done by an external force in moving a charge from infinity to that point.

## Electrostatic Potential

- Electrostatic potential at any point in a region of electrostatic field is the minimum work done in carrying a unit positive charge (without acceleration) from infinity to that point.
- Electric potential due to a point charge of magnitude  $q$  at a distance  $r$  from the charge is given as  $V = \frac{q}{4\pi\epsilon_0 r}$
- Potential difference between two points P and R can be written as  $V_P - V_R = \frac{U_P - U_R}{q}$

## Equipotential Surfaces

- An equipotential surface is that surface at every point of which, the electric potential is same.
- No work is done in moving a test charge from one point of the equipotential surface to the other.
- The equipotential surface for a point charge are concentric spherical surfaces centered at the charge.

## Potential due to a System of Charges

- For a system of point charges  $q_1, q_2, q_3, \dots, q_n$  at distances  $r_1, r_2, r_3, \dots, r_n$  respectively from the point P,
- The potential at a point P is given by the superposition principle

$$V = \frac{1}{4\pi\epsilon_0} \left( \frac{q_1}{r_1} + \frac{q_2}{r_2} + \frac{q_3}{r_3} + \dots + \frac{q_n}{r_n} \right)$$




$$V = \frac{1}{4\pi\epsilon_0} \sum_{i=1}^n \frac{q_i}{r_i}$$

## Dipole

- A dipole is a system of two charges of equal magnitude  $q$  and opposite polarity separated by a distance  $2a$ . The dipole moment of the dipole is  $\vec{p} = q \times 2a$  with magnitude  $p = q \times 2a$  and direction -  $q$  to  $+q$ .

### Potential due to dipole.



- Potential at point P due to charge at point A is given as:

$$V_1 = \frac{-q}{4\pi\epsilon_0 r_1}$$

- Potential at point P due to charge at point B is given as:

$$V_2 = \frac{q}{4\pi\epsilon_0 r_2}$$

- Total Potential at point P due to dipole

$$V = V_1 + V_2$$

$$V = \frac{q}{4\pi\epsilon_0} \left[ \frac{1}{r_2} - \frac{1}{r_1} \right]$$

$V$  at position vector  $\vec{r}$  can be expressed as

$$V = \frac{\vec{p} \cdot \hat{r}}{4\pi\epsilon_0 r^2} \quad \text{for } (r \gg a)$$

### Potential Energy of a Single Charge

- It is the work done in bringing a charge  $q$  from infinity to a point  $P$  whose position vector is  $\vec{r}$  and  $V(\vec{r})$  is potential due to external field there.
- The magnitude of work done  $= q \cdot V(\vec{r})$ .

### Potential Energy of a System of Two Charges in an External Field

- It is the sum of the work done in bringing  $q_1$  and  $q_2$  from infinity to  $\vec{r}_1$  and  $\vec{r}_2$  respectively and assembling the charges at their respective locations.

$$U = W_1 + W_2 + W_3$$

$$U = q_1 \cdot V(\vec{r}_1) + q_2 \cdot V(\vec{r}_2) + \frac{q_1 q_2}{4\pi\epsilon_0 r_{12}}$$

### Potential Energy of an Electric Dipole, When Placed in a Uniform Electric Field

- The potential energy of an electric dipole in a uniform electric field is given as  $U = -\vec{p} \cdot \vec{E}$  where  $\vec{p}$  = dipole moment of the dipole  $\vec{E}$  = strength of external electric field

### Electrostatics of conductors

- Inside a conductor, the electric field is zero.
- The interior of a conductor can have no excess charge in static situation.
- The electric field on the surface of a charged conductor is perpendicular to the surface of the conductor at every point.
- Electrostatic potential is constant throughout the volume of the conductor, and has the same value as on its surface.

### Non-Polar Dielectrics

- When the Non-polar dielectric is placed in an external electric field the two centres of positive and negative charges in the molecule are separated and the non-polar molecule gets polarised.

### Polar Dielectrics

- When an external electric field is applied, the individual dipole moments tend to align with the field.



- A net dipole moment in the direction of the external field is developed

- Induced dipole moment  $P$  acquired by the molecule may be written as  $P = \alpha \epsilon_0 E_0$

When a dielectric is placed in an external electric field  $\vec{E}_0$  due to polarisation there is development of an electric field  $\vec{E}_p$  opposite to the  $\vec{E}_0$

$\therefore$  Effective electric field in a polarised dielectric =  $E = E_0 - E_p$

## Capacitor

- A capacitor is a system of two conductors separated by an insulator.
- Its capacitance,  $C = Q/V$ , where  $Q$  and  $-Q$  are the charges on the two conductors and  $V$  is the potential difference between them.
- $C$  is determined purely geometrically, by the shapes, sizes and relative positions of the two conductors. For a parallel plate capacitor (with vacuum between the plates),

$$C = \epsilon_0 A/d$$

Here,  $A$  is the area of each plate and  $d$  is the separation between them.

- If the medium between the plates of a capacitor is filled with an insulating substance (dielectric), the electric field due to the charged plates induces a net dipole moment in the dielectric. This effect is called polarisation and it gives rise to a field in the opposite direction.
- The net electric field inside the dielectric, and hence the potential difference between the plates, is thus reduced. Consequently, the capacitance  $C$  increases from its value  $C_0$  {when there is no medium (vacuum)} to  $C = KC_0$ . Here,  $K$  is the dielectric constant of the insulating substance.
- Capacitors are of the following types:
  - Parallel plate capacitor
  - Cylindrical capacitor
  - Spherical capacitor
- Capacitance of cylindrical capacitor without dielectric is given as  $C = 2\pi\epsilon_0 l \ln(b/a)$   
 Capacitance of spherical capacitor without dielectric is given as  $C = 4\pi\epsilon_0 ab/(b-a)$

## Capacitors in Series

- In series connection the potential difference applied across the combination is the sum of the resulting potential differences across each capacitor.

- In series combination the charge in all of the capacitors is same.
- Total capacitance in a series combination of the capacitors is given as:

$$\frac{1}{C_s} = \frac{1}{C_1} + \frac{1}{C_2} + \frac{1}{C_3}$$

### Capacitors in parallel

- In parallel connection the potential difference is same across each capacitor.
- Total capacitance in parallel combination of the capacitors is given as:

$$C_p = C_1 + C_2 + C_3$$

- The Energy  $U$  stored in a capacitor of capacitance  $C$ , with charge  $Q$  and voltage  $V$  is

$$U = \frac{Q^2}{2C}$$

$$U = \frac{1}{2} CV^2$$

### Van de Graff generator

- It works on the principle that charge given to a hollow conductor is transferred to the outer surface and is distributed uniformly on it.  
It is a device used for building up high potential differences of the order of a few million volts. It consists of a large spherical conducting shell. By means of a moving belt and suitable brushes, charge is continuously transferred to the shell and potential difference of the order of several million volts is built up.  
It is used as a particle accelerator.